

Keystrokes in *SilverFast*

Action	Macintosh	Windows
Description of keyboard shortcuts and their respective counterparts		
Command.....	Command-/Apple-Key	–
Alt.....	Opion-/Alt-Key	Alt-Key
Shift	Shift-Key	Shift-Key
Ctrl.....	Control-/Ctrl-Key	Control-/Ctrl-Key
Return	Return-/Enter-Key	Return-/Enter-Key
Esc.....	Escape-/Esc-Key	Escape-/Esc-Key

ScanPilot / ImagePilot

Apply / Execute current tool	Return	Return
Scroll / Next action	Up and Down arrow	Up and Down arrow

Prescan, scan / Preview, process

Stop prescan / stop scan.....	Command+Period.....	Strg+Period
Switch to other colour space.....	Ctrl+Click on.....	Right mouse button+Click on
	Scan-/Process-button	Scan-/Process-button
Zoom	Ctrl+Click&Drag	Ctrl+Click&Drag

Image frames

Duplicate frame	Alt+Click&Drag.....	Alt+Click&Drag
Entire Window in one frame	Command+A	Ctrl+A
Delete frame (extended keyboard).....	Delete	Delete
Delete frame (normal keyboard).....	Alt+Backspace.....	Delete
Frame reset	Reset-button.....	Reset-button
Copy settings of one frame	Alt+Click on active frame,	Alt+Click into inactive
into an other frame	click then into target frame ..	target frame

Action

Macintosh

Windows

Auto-adjust

Resetting auto-adjust	Alt+click on	Alt+Click on
	Auto-adjust button	Auto-adjust button

Highlight / shadow / midtone tool (HSM-tool)

Set highlight	Click on white triangle of HSM-tool
Set midtone	Click on pipette of HSM-tool
Set shadow	Click on black triangle of HSM-tool

Multiple attempts with pipette

Hold down pipette for multiple	hold down Alt	hold down Alt
attempts (only highlight, shadow)		
Reset highlight / shadow	Alt+Pippette of HSM-tool	
Display brightest point	 Click on white square	F6
Display darkest point	 Click on black square	F5

Histogram

Show result histogram	Alt in the histogram dialogue.	Alt in the histogram dialogue
-----------------------------	--------------------------------	-------------------------------

Selective colour correction

Select all colours	Command+A	Ctrl+A
Select additional colour	Shift+Click into prescan	Shift+Click into prescan
Select additional colour column	Shift+Click on LED	Shift+Click on LED
	below column.	below column
Show inactive mask area	F7	F7
(dialogue must be closed)		

Reset

Reset all parameters	Shift+Click on Reset-button ..	Shift+Click on Reset-button
Frame reset.	Alt+Click on Reset-button. ...	Alt+Click on Reset-button
Undo/Redo last operation	Command+Z	Ctrl+Z

Action	Macintosh	Windows
Opening a dialogue window		
Zoom in preview	Command+1	Ctrl+Alt+1
Image auto-adjust	Command+2	Ctrl+Alt+2
Histogram dialogue.....	Command+3	Ctrl+Alt+3
Gradation dialogue	Command+4	Ctrl+Alt+4
Global colour correction.....	Command+5	Ctrl+Alt+5
Selective colour correction.....	Command+6	Ctrl+Alt+6
Expert dialogue	Command+8	Ctrl+Alt+7
Leave dialogue/Leave SilverFast	ESC or Command+Period ...	ESC or Ctrl+Period
Start scan / Process image	Return/Enter.....	Return/Enter

Main dialogue

Undo/Redo last action	Command+Z	Ctrl+Z
Show current hardware resolution	Ctrl	F5
Show calculated scan resolution	Ctrl+Shift	F6

Masks in *SilverFastSRD*

Hide mask frame.....	Ctrl	Ctrl
Shade inactive mask area	Alt+Ctrl.....	Alt+Ctrl
Reduce mask.....	Alt.....	Alt
Extend mask.....	Shift	Shift

JobManager

Select all job entries	Command+A	Ctrl+A
------------------------------	-----------------	--------

Action

Macintosh

Windows

VLT (virtual light table)

Context menu in album and overview ..	Ctrl+Click	Right mouse
Preview mode, full screen,	Command+Shift+F	Ctrl+Shift+F
fit to screen		
Display EXIF infos	Command+I	Ctrl+I
Album, mark all images	Command+A	Ctrl+A
Album, delete image	Command+backspace	Ctrl+backspace

EP (extended printing dialogue)

Crop opposing edges / corners	Shift+Click&Drag	Shift+Click&Dra simultaneously
-------------------------------------	------------------------	-----------------------------------

SilverFast Launcher

Terminate	Command+Q	Ctrl+Q
-----------------	-----------------	--------